


● [PHP FOR WIN2003 Server IIS6 安裝方法與步驟]

事前準備工作：

請先將你的 IIS 套件安裝完成,並確定你的 IIS 的運作是正常的，測試方法可以在你的網址列輸入 <http://127.0.0.1> 若看到如下畫面：



即代表你的 IIS 運作是正常的，可以準備接下來的 PHP 程式安裝

步驟 1：

下載 PHP 4.4.1 installer

PHP 4.4.1 installer 下載位置:

<http://tw2.php.net/get/php-4.4.1-installer.exe/from/tw.php.net/mirror>


下載 PHP 4.4.1-Win32.zip

<http://ftp.isu.edu.tw/pub/Unix/Web/PHP/distributions/php-4.4.1-Win32.zip>

步驟 2：


安裝 PHP 4.4.1 installer

請按 [Next>]




步驟 3 :

選擇 “Standard” 後按[Next >]



步驟 4 :

請按 [Next>] 安裝路徑為 C:\PHP\ (可更改為你想要的路徑)


**步驟 5：**

輸入 SMTP 主機及管理者電子信箱，這時你可以隨意輸入：


SMTP 主機：abc.com.tw (或輸入你的郵件主機 IP 位址)

管理者信箱：abc@abc.com.tw (或輸入你的郵件信箱)

輸入完畢之後，請按 [**Next>**]

**步驟 6：**

請選擇 “IIS6” 後按[Next >]




步驟 7 :

程式安裝時的畫面



安裝完成的訊息




步驟 8 :

安裝完成後，請將下載的 PHP 4.4.1-Win32.zip 檔案解壓縮到 C:\PHP，並且 Copy C:\PHP\資料夾下的“php4ts.dll”和 C:\PHP\sapi\資料夾下的“php4isapi.dll”到 C:\Windows\System32\


步驟 9 :

接下來，請利用文字編輯器（記事本或 WordPad）開啓 C:\windows\php.ini，使用編輯器的尋找功能搜尋 register_globals 字串




步驟 10 :

找到 register_globals = Off 將其參數改爲 register_globals = On 後，請將檔案儲存




步驟 11 :

請點選 [開始]>[設定]>[控制台]>[系統管理工具]>[網際網路資訊服務(IIS)管理員]，打開網際網路資訊服務管理畫面，選擇網頁服務延伸>點選“新增網頁服務延伸...”




步驟 12：

點選之後請輸入延伸名稱，並新增你的 PHP 的執行檔案（預設是 C:\PHP\php.exe），並且打勾設定延伸狀態成允許後，按[確定]



步驟 13：

利用文字編輯器編輯一個名為 test.php 的檔案，檔案內容如下：


A screenshot of a Notepad window titled "test.php - 記事本". The window has a menu bar with "檔案(F)", "編輯(E)", "格式(O)", "檢視(V)", and "說明(H)". The text area contains the following PHP code:

```
<?
phpinfo();
?>
```

步驟 14 :

將檔案儲存到網頁的預設資料夾 **C:\inetpub\wwwroot** 中

打開瀏覽器在網址列輸入 <http://127.0.0.1/test.php> 若看到下面的畫面，表示 PHP 是正常運作的



The screenshot shows a Microsoft Internet Explorer browser window displaying the output of the PHP function `phpinfo()`. The browser's address bar shows the URL `http://127.0.0.1/test.php`. The main content area features a blue header with the text "PHP Version 4.4.1" and the PHP logo. Below this is a table of system and configuration details.

System	Windows NT WIN2003SRV 5.2 build 3790
Build Date	Oct 30 2005 12:44:57
Server API	CGI/FastCGI
Virtual Directory Support	enabled
Configuration File (php.ini) Path	C:\WINDOWS\php.ini
PHP API	20020918
PHP Extension	20020429
Zend Extension	20050606
Debug Build	no
Zend Memory Manager	enabled
Thread Safety	enabled
Registered PHP Streams	php, http, ftp, compress.zlib

At the bottom of the page, it states "This program makes use of the Zend Scripting Language Engine:" followed by a "Powered by" logo.

【 哈堤生活館-優化你的生活 <http://www.hatea.com.tw> --Dark Skyline 】